# Edit or Delete the Parameters of a Generated Client

There are many reasons why you would want to change the parameters of your connection client: your TSplus server IP address changed, you need to add printer's redirection, to change the universal printer settings or so on...

- You first need to create a shortcut of the ConnectLauncher.exe file, located on the RDP6 folder of the user's profile:

.

- Then, right click on it and hit properties. Place your mouse at the end of the "target" field and type in the client's path followed by "/?", for example: *"C:\Users\John\Desktop\clientname.connect /?"*:

Now click OK and double click on the shortcut. A list of switch appears :

Remote Desktop possible parameters

/clean : to reset user workstation parameters

Connection settings
-user: user logon
-psw: user password
-server: server IP adress
-port: RDP port number (3389)
-domain: Domain name
Display settings
-color: Enter 8, 15, 16 or 24 (bits)
-full: 2 for full screen, else enter 1
-width: enter 800, 1024 or 1280
-height: enter 600, 768 or 1024
-remoteapp: on/off to do Microsoft RemoteApp
-seamless: on/off to do seamless Remote Application
-dualscreen: on/off to use a dual screen
-alttab: 0/1 - 0 means Alt-Tab on the client side
-localtb: 0 or 42 - 0 means RDP will cover the local taskbar
-apppath: path of a specific RemoteApp

Local drives settings
-disk: on/off Disks
-printer: on/off Printers
-com: on/off COM ports
-smartcard: on/off Smart cards

Universal Printer settings
-preview: on/off Preview the prints on the local PC
-select: on/off Select a local printer
-default: on/off Print on the default local printer

-defaultsystem: on/off Print on the default local printer with the system
defined PDF reader

Security settings
-lock: lock the program on the workstation name
-serial: lock the program on the device serial number
-gatewayhostname: RD Gateway hostname
-gatewayusagemethod: RD Gateway usage method

OK

Click OK, the list of all the parameters appears in a small window.
You can now edit them to match your preferences, you will need to log off and log on again to apply the changes.

Changing the connection settings of this lo...

To modify the local connection settings
just replace the current ones.

altb 42 -full 2 -remoteapp off -seamless off -width 1024 -height 768 -smartsizing 0

OK   Cancel

Clean the Parameters of a Generated Client

After having launched the client at least once, you can clean the parameters by deleting the client.txt file located in the RDP6 folder: