

Load Balancing Feature


Pre-requisites

Using this feature, you will be able to manage a load balanced environment.

It means that the load of all your users will be distributed between your servers. The workload will be shared between all the servers of your farm.

Load Balancing enables to use an unlimited number of servers with load balancing, and is available with the Enterprise edition (one valid license per server). This very powerful and advanced capability is to be used when a large number of users/servers has to be deployed.

Warning : Load Balancing is not compatible with the Gateway Feature (allowing you to assign servers to users/groups, see [this documentation](#) for more information.)



Usually we recommend using one server for 50 concurrent users. For standard commercial application written in VB, C, C++, Delphi or Uniface you can go up to 100 concurrent users especially if you decide to use XP 64-bit which, according to our experience, tops most operating systems delivered by Microsoft. XP or Windows 7 are much more stable operating systems. For W7, we recommend to use the 64-bit version.


Generated Clients and Web Access

There are three ways to connect to a Load Balanced cluster:

- Using a **Generated Client** (executable program, created by the [Portable Client Generator](#))
- Using a **Web Portal Access** by activating it on the Web Portal Preferences window.
- With the [TSplus App](#) from your mobile device.

Load Balancing Main Window

The Load Balancing Manager can be found under the Farm Tab of the AdminTool:



The main window allows you to configure Load Balancing. It lists all the servers in your Load Balanced server farm, and allows you to add a new server (by clicking on the "Add a new Server" button) or displays an existing server (by clicking on it). It also allows you to enable, disable and configure the Load Balancing (more on this below).

Click on the buttons in the picture below to access the corresponding information:


Load Balancing type unknown

Enabling/Disabling Load Balancing


On top of the Load Balancing window, you will see a big button:

- This button displays the current state of the Load Balancing.
- If you click on it, it will enable or disable the Load Balancing depending on its current state.

Here is the button when the Load Balancing is **Disabled**. A click on it will activate it and disable the [Users/Servers Assignment](#).



Here is the button when the Load Balancing is **Enabled**. A click on it will deactivate it and enable the [Users/Servers Assignment](#).



How does Load Balancing choose a server?


When Load Balancing is enabled, the user will be sent to the less loaded server at the time of his connection.

Configuring the Computation of Servers' Loads

To determinate which is the less loaded server, the load of every server is computed using a weighted average between several performance indicators:

- number of connected users
- processor usage
- memory usage
- disk usage

You can modify the weight (importance) of these indicators by using the following sliders:



Using these sliders, you will be able to fine-tune the Load Balancing, and to optimize it to your own needs. For instance if your users launch a business application with big memory requirements, it might be a good idea to increase the impact of the RAM in the load computation using the "Memory" slider.

You can also reset these values by clicking on the "Back to Default Settings" button.

How is Server's Load computed?

The load of each server is computed when needed in order to decide on which server the user must be sent.

For this computation, we use a **weighted average** between 4 hardware metrics.

The 4 sliders allow you to give more (or less) weight on each of these metrics, which are:

- Users : number of connected users
- CPU : percentage of non-idle processor time
- Memory : percentage of used memory
- I/O : percentage of non-idle disk time


For example, if you put the "Memory" slider on its right side and all the other sliders on their left side, the load of each servers will be computed using almost only the percentage of used memory - and your users will be sent to the server having the most available memory.

- When a slider is completely on the left, the weight used in load computation will be 1.
- When a slider is completely on the right, the weight used in load computation will be 100.

Moreover, the load of a given server depends on the ratio [used resources / total resources] ; so if a server A is twice as powerful as a server B, twice more users should be sent to server A than to server B (all other things being equals).

Adding a new Server


To add a new server, simply click on the "Add a new Server" button. The following window will be displayed:



- The "Display Name" is the title that will be shown to your users on the Web Access HTML page. It is supposed to be more user-friendly than a technical value (such as an IP), for instance "US Server" or "Blue Zone".
- The server address is reachable with http or https ports.
- When using Load Balancing, the "RDP Port" will not be used. It is only used when connecting using a Generated Client. We advise you to keep the default setting ("Same as web").
- You also have the possibility to enable or disable the server.


Load-balance only on user's assigned servers

Load-balancing can also be done directly on user's assigned server using the checkbox "Balance on user's assigned servers". As a result, you will be able to load-balance on accounting department servers only for accountant users, once these specific servers have been assigned to the accountant users.



Editing an existing Server

To modify an existing server, simply click on the "Edit" button of the server you want to update. The following window will be displayed:




The progress bar shows the current load of the server. It also confirms you that the server is well configured and can be contacted by the Gateway.

Load Balancing using a Connection Client

You are not using the Reverse Proxy role of the Gateway (default case)

This is the default case if you just installed Terminal Service Plus. In this case, if **you want to generate a [Connection Client](#) to connect to a given Application server**, then:

- Do not check the "Use Load-Balancing" checkbox on the on the Gateway Portal tab of the Connection Client Generator,



The screenshot shows the 'Windows Client Generator' dialog box with the 'Load-Balancing' tab selected. The 'Enable Load-Balancing ?' section contains an unchecked checkbox for 'Use Load-Balancing' and a text field for 'Gateway Web port number' set to '80'. Below this, explanatory text states: 'When "Use Load-Balancing" is checked, it enables using the Gateway with Load-Balancing to connect to an Application Server of the fam. Prior using this advanced feature, please read our documentation'. At the bottom, the 'Client location' is 'C:\Users\Admin\Desktop' with a 'Browse' button, and the 'Client name' is 'john.connect'. A 'Create Client' button is on the right.

Windows Client Generator

General Display Remote Desktop client Seamless client Local resources Program Security **Load-Balancing**

Enable Load-Balancing ?

☐ Use Load-Balancing Gateway Web port number

When "Use Load-Balancing" is checked, it enables using the Gateway with Load-Balancing to connect to an Application Server of the fam.

Prior using this advanced feature, please read our documentation

Client location:

Client name:

- Use the public IP address or hostname of your Application Server directly in the "Server" field.

However, if **you want to generate a [Connection Client](#) to connect to the less loaded server** and use Load Balancing, then:

- Check the "Use Load-Balancing" checkbox on the Connection Client Generator,

The screenshot shows the 'Windows Client Generator' dialog box with the 'Load-Balancing' tab selected. A red rectangle highlights the 'Enable Load-Balancing ?' section, which contains a checked checkbox labeled 'Use Load-Balancing' and a text field for 'Gateway Web port number' set to '80'. Below this, explanatory text states: 'When "Use Load-Balancing" is checked, it enables using the Gateway with Load-Balancing to connect to an Application Server of the farm. Prior using this advanced feature, please read our documentation'. At the bottom, there are fields for 'Client location' (C:\Users\Admin\Desktop) and 'Client name' (john.connect), a 'Browse' button, and a 'Create Client' button.

- Use the public IP address or hostname of your Gateway Server directly in the "Server" field.


You are using the Reverse Proxy role of the Gateway ("/~/" in URL)

See [this page](#).

Activating the Load Balancing for a Gateway Portal access

Activating Load Balancing is really easy. It only takes three steps:

- 1) Generate a Web Access page with the option "Generate a Gateway Portal enabled Web Page" checked, by clicking on the Web Portal Preferences tile of the Web tab:



Preferences

Default Values

Login:

Password:

Domain:

☒ Show the Domain field ☒ Remember last login

Advanced

Keyboard:

Access Type

Available Clients: ☒ HTML5 (iPad, iPhone, Android devices, computers)
☒ RemoteApp (Windows PCs)

Gateway Portal: ☒ Generate a Gateway Portal enabled Web Page

Upload: Folder to select files.

☒ User Desktop (default)
☐ My Documents
☐ WebFile folder
☐ Custom folder:

Folder path from where the user will select files to be uploaded.

Download: Folder for all received files



☒ User Desktop (default)
☐ My Documents
☐ WebFile folder
☐ Custom folder:

Folder where all downloaded files will be stored on the Server.


Downloaded files from the users PC will be stored in the specified folder.
(Drag/Drop from the user PC, Download button or File Transfer button)

☒ Use Explorer to select files ☐ Use TSplus GUI

- 2) Enable Load Balancing by clicking on the "Enable/Disable Load Balancing" button (on the Load Balancing Manager, located on the Farm tab of the AdminTool):




- 3) Open a browser and navigate to the Web Access page you generated in step 1 (by default: <http://localhost/index.html>). After typing a login, you will see that **the Web Access page choose the less loaded server of your farm**:



Activating the sticky session feature

Regardless of your connection method, you will always be able to activate the sticky session feature by clicking on the right button of the Load balancing window:



It will allow you to reconnect to a disconnected session instead of opening a new session on a different server.