# Advanced Features - Product

#### Overview

On this tab, you can modify TSplus settings by adding an AdminTool Pincode, use the Windows RDS role and customize the background color and language of the AdminTool.

TSplus - Administration Console	1			- 0	×
TSPLUS	Remote Access Manage	ement Console			
П НОМЕ	Backup / Restore you	r Server Parameters			
	Advanced Settings	Name	Value		
S WEB	Security Security Session	Administrator pin code Use RDS role AdminTool Language	Default () Default (No) English		
FARM	Contextual menu 🕸 Logs	Adminior cangaage	Ligion		
SESSIONS					
SYSTEM TOOLS					
ADVANCED					
값 ADD-ONS					

#### Administrator Pin Code

The Administrator can secure the Administrator Tool access by setting a pin code which will be asked at every start, on the Advanced tab of the AdminTool, under the Product Settings:

<b>1</b> 8 I	Splus - Administration Console	- 100						_	$\times$
	TSPLUS	Rem	ote Access Mar	ageme	nt Console				
命 □	HOME		Backup / Restor	e your Serve	r Parameters				
¢	PRINTER		Advanced Settings		Name		Value		
S	WEB		Security Session		Administrator pin code		Default ()		
	FARM				A Administrator pin code				
	SESSIONS SYSTEM TOOLS				AdminTool will ask for a password i	if this value is not empt	ty.		
墩	ADVANCED								
చి	ADD-ONS				Value: 1234		<u> </u>		
©7	LICENSE			Save	Ca	ncel			

#### Use RDS role

Multi-session role and Windows RDS role are not compatible. You can either select the Windows RDS role, or TSplus Multi-session role.

- When using Multi-session role, the Windows RDS role must be uninstalled.
- When using the Windows RDS role, this Windows role must be installed.

**WARNING**: changing role requires to reboot the system. When selecting the Windows Remote Desktop, only one user at a time will be allowed on a workstation system.

Description:		
You can either session role. - When using uninstalled. -When using t installed.	role and Windows RDS role are not compatible. select the Windows RDS role, or TSplus Multi- Multi-session role, the Windows RDS role must be he Windows RDS role, this Windows role must be anging role requires to reboot the system.	~
Value:		

# 

To use the Windows RDS role, select the "Yes" value and Save.

## Modify the AdminTool Background color

Customize AdminTool's background color using an hexadecimal code (for example: 0xFFFFFF).

🗱 TSplus - Edit Setting				
AdminTool background color				
Description:				
Customize AdminTool's background color using an hexadecimal code (for example: 0xFFFFF).				
	$\sim$			
Value:				
0xFFFFFF				
Save Cancel				

## Modify the AdminTool Language

Select your preferred language for the AdminTool among the 21 available.

🛺 TSplus - Edit Setting					
AdminTool Language					
Description:					
Set the AdminTool interface language.	~				
Value:					
English	~				
English					
French					
German					
Dutch					
Spanish Italian					
Portuguese					
Polish					
Russian					
Ukrainian					
Hungarian					
Czech					
Turkish Chinese					
Traditional Chinese					
Japanese					
Korean					
Arabic					
Farsi					
Hebrew					
Amenian					